

Department of Computer Science 2018/2019

UK CLIMATE ANALYSIS

User Guide Manual

In Collaboration With



Module Supervisor:

Bane, Michael

Hartree Centre Supervisor:

Pipe, Mark

Members of Team Gamma:

Al Lawati, Aqil - 201364339

He, Zezhong - 201338647

Patel, Aamir - 201351019

To get started with the project, a user must follow the following instructions:

- 1. A user must have **access to Hartree Centre Safe Account**. Unless you are granted with the credentials from Hartree, you cannot proceed.
- 2. The next step would be to **follow the user guide provided by Hartree** (attached in the **folder**). It is necessary to set up private keys and public keys on user's local machine. Once done, upload the public key to Hartree's SAFE account.

3. Update SSH configuration file:

Go to file directory "C:\Users*\.ssh\" and open "config" file.



Add below code and replace "%USERNAME" with Hartree Username.

Host login1 Hostname login1.dawson.hartree.stfc.ac.uk
Host bicluster1
User %USERNAME%
Hostname bdb209
ProxyCommand ssh -A %r@login1 -W %h:%p
Jupyterlab
LocalForward 8888 localhost:8888
LocalForward 8889 localhost:8889
LocalForward 8890 localhost:8890
LocalForward 8891 localhost:8891
LocalForward 8892 localhost:8892
LocalForward 8893 localhost:8893
LocalForward 8894 localhost:8894
LocalForward 8895 localhost:8895
LocalForward 8896 localhost:8896
LocalForward 8897 localhost:8897
LocalForward 8898 localhost:8898

4. Accessing Hartree HPC machine:

Open Command Line Prompt and run below command. If your ssh key is set up correctly you will not be asked for any password. The prompt should indicate you are logged into bdb209.

ssh bicluster1

Run the following once - it will write some stuff to your .bashrc to configure python.

/usr/local/bin/set_anaconda.sh

Copy the following into your .bashrc to set your Java home directory, to configure spark, and to configure pyspark to use Jupyter Lab.

export JAVA_HOME=/usr/jdk64/jdk1.8.0_112 export HDP_VERSION=2.6.4.0-91 export SPARK_MAJOR_VERSION=2 export PYSPARK_DRIVER_PYTHON=jupyter export PYSPARK_DRIVER_PYTHON_OPTS=lab

Then source the .bashrc file. This only needs to be done once. On subsequent logins this will run automatically.

source .bashrc


5. How to open PySpark platform?

Open PySpark platform and open the highlighted link in any browser

pyspark


```
axa19-kkr16@bdb209:~
                                                                                                                          [axa19-kkr16@bdb209 ~]$ pyspar
SPARK_MAJOR_VERSION is set to 2, using Spark2
 [ 15:32:44.976 LabApp] Writing notebook server cookie secret to /run/user/7010/jupyter/notebook_cookie_se
 I 15:32:45.132 LabApp] The port 8888 is already in use, trying another port.
   15:32:45.140 LabApp] JupyterLab extension loaded from /opt/anaconda3/lib/python3.7/site-packages/jupyte
rlab
I 15:32:45.140 LabApp] JupyterLab application directory is /opt/anaconda3/share/jupyter/lab W 15:32:45.142 LabApp] JupyterLab server extension not enabled, manually loading... I 15:32:45.144 LabApp] JupyterLab extension loaded from /opt/anaconda3/lib/python3.7/site-packages/jupyte
  15:32:45.144 \ Lab App] \ Jupy ter Lab \ application \ directory \ is \ /opt/anaconda3/share/jupy ter/lab
   15:32:45.145 LabApp] Serving notebooks from local directory: /bdusers/HCP053/kkr16/axa19-kkr16
   15:32:45.145 LabApp] The Jupyter Notebook is running at:
  15:32:45.145 LabApp] http://localhost:8889/?token=53ea46824fae6f200d6ec897f25f54479836c0e174a8fbd6
15:32:45.145 LabApp] Use Control-C to stop this server and shut down all kernels (twice to skip confirm
ation).
[W 15:32:45.148 LabApp] No web browser found: could not locate runnable browser.
[C 15:32:45.148 LabApp]
    To access the notebook, open this file in a browser:
         file:///run/user/7010/jupyter/nbserver-20349-open.html
        copy and paste one of these URLs:
        http://localhost:8889/?token=53ea46824fae6f200d6ec897f25f54479836c0e174a8fbd6
```

Copy the highlighted link and paste it any browser





6. Upload the "ClimateAnalysis" Jupyter Notebook

Click on Upload Button.



Select "ClimatAnalysis.ipynb" Jupyter Notebook and click open.





7. How to run Jupyter Notebook?


Run the first cell by selecting the cell and click on below button or press Shift + Enter.

```
Launcher
                              ■ ClimateAnalysis.ipynb
                                 Code
      [1]: %%time
           from io import StringIO
           import itertools
           import numpy as np
           import pandas as pd
           from pandas import Series
           from pandas import concat
           from pandas.plotting import lag_plot
           from pandas.plotting import autocorrelation_plot
           import statsmodels.api as sm
           from statsmodels.graphics.tsaplots import plot_acf
           from statsmodels.tsa.ar_model import AR
           from sklearn.metrics import mean_squared_error
           import matplotlib.pyplot as plt
           %matplotlib inline
           fig = plt.figure(figsize = (40,10))
           plt.style.use('fivethirtyeight')
           warnings.filterwarnings("ignore")
           spark = SparkSession.builder.appName('climateChange').getOrCreate()
           def readFiles (feature):
               def process(tup):
                   def convertTuple(tup):
                       str = ''.join(tup)
```

Select any hypothesis and then run the cell.

```
%%time
# WINTER GETTING WETTER
runPredictionDaily("rainfall", "winter")
# RESULT: Correctly Predicted
# SNOWFALL DURING WINTER DECREASING
runPredictionMonthly("snow-falling", "winter")
# RESULT : Unpredictable
# SUMMER GETTING DRIER
runPredictionDaily("rainfall", "summer")
# Result: Correctly Predicted
%%time
# SUMMER GETTING WARMER
runPredictionDaily("maximum-temperature", "summer")
# Result: Correctly Predicted
# ANNUAL SUNSHINE INCREASING
runPredictionMonthly("sunshine", None)
# Result: Correctly Predicted
```

The output will be displayed below the cell.



Quick Start for Dash Plotly

At first, you need to install Dash Plotly in your local computer. In order to do this, you need to open CMD on your computer, run

```
pip install dash==0.42.0  # The core dash backend
pip install dash-daq==0.1.0  # DAQ components (newly open-sourced!)
```

After several minutes (this is depending on your computer and network speed), you have completely installed the Dash Plotly.

Then, you should put all the code and .csv file in same folder.

Go to this folder by using CMD and the code 'cd' + 'file path'

```
C:\Users\dell>cd DashPlot
C:\Users\dell\DashPlot>
```

Run the code by entering 'python Dash.py' and after several minutes, a link would appear on your screen;

```
C:\Users\del1\DashPlot>python Dash.py
Rumning on http://127.0.0.1:8050/
Debugger PIN: 761-136-173

* Serving Flask app "Dash" (lazy loading)

* Environment: production

WARNING: Do not use the development server in a production environment.

Use a production WSGI server instead.

* Debug mode: on
```

Finally, copy the link and paste it in a browser. You should see an app, and this means Dash Plotly is running successfully.

